

WPSPro 3.0: Upgrading to Version 3.0

 $\ensuremath{\mathbb{C}}$ 2020. DNP Imaging comm America Corp.

Last Updated: 09/18/2020

All rights reserved.

Rev: 02

Contents

Introduction	3
Section 1: Download the WPS Pro 2.x to 3.0 Updater Files	3
Section 2: Prepare USB Drive for Installation	3
Section 3: Updating Your Console	6
Contact Us	.15

Introduction

Follow these instructions to upgrade your WPS from version 2 to version 3 software.

NOTE:

This is for DNP IAM customers only.

Section 1: Download the WPS Pro 2.x to 3.0 Updater Files

User instructions here for accessing the files via the website.

1. From your browser, navigate to the following URL:

http://dnpphoto.com/en-us/Support/Legacy-Equipment/Legacy-Drivers-and-Tools

- 2. Under the Legacy Wireless Print Server section, download the update file. This file downloads as a zip file.
- 3. Make note of where the file downloads to on your PC.

Section 2: Prepare USB Drive for Installation

The USB Drive must have at minimum of 4GB space.

1. Insert USB into your PC and Format the drive by right clicking on USB Drive.



2. Select Format and then click on the Start button.



Format USB Drive (F:)	×
Capacity:	
28.6 GB	\sim
File system	
FAT32 (Default)	\sim
Allocation unit size	
16 kilobytes	\sim
Restore device defaults	
Volume label	
Format options	
Quick Format	
Start Close	

3. Locate the zipped files you downloaded and extract the WPS Pro software.



4. Copy the extracted files to your USB drive:



Section 3: Updating Your Console

There are several steps to this update. Each step must be performed *and performed in the correct order*, as detailed below.

1. Insert the USB Drive into USB slot 4.



- 2. Enter Maintenance mode via hidden menu.
 - a. Tap the **HOME** icon.

DSRX1HS Printing	Pending Jobs	Completed Jobs
696 6x4 (PC)		
CONFIGURATION		Job. 427 via POST-w288h432 to RX1HS = POST- w288h432
VPS 2.0 fer 2.0 20160815 0 9 0 SID WPS8afe		DN

b. Tap the upper right corner of the screen to go to the Hidden Menu.



c. Tap WPS Maintenance.

WPS Maintenance						
? WPS Status		/				
DNP Launcher						
Settings						
File Manager						
Linux Deploy						
QuickSupport						
	⇔	6	Û	ā	↓ »	

d. Tap Enter Maintenance Mode.

WPS Maintenance Ready ENTER MAINTENANCE MODE SHUTDOWN WPS BOX	

e. Type **1234** and tap **OK**.

Saving screenshot	WP5 Manageman	
	Password	
	789	
	СООК	
4 >		

- 3. Begin the file copy process:
 - a. Tap Restore WPS (it may take up to 10 seconds for the options to show.)

	03:22
WPS Maintenance	
Ready	
EXIT MAINTENANCE MODE	
RESTORE WPS (USB)	
RESTORE WPS	
SHUTDOWN WPS BOX	
	DNP
	Photo imaging

b. Wait for the file to copy. (This process takes approximately 5-6 minutes.)



c. After linux.img is completed, you will return to the maintenance screen.

	03:18
WPS Maintenance Ready	
EXIT MAINTENANCE MODE	
RESTORE WPS (USB)	
RESTORE WPS	
SHUTDOWN WPS BOX	
CLOSE	DNP Photo Imaging

4. Reboot the WPS by holding down the power button. Keep the USB Drive Inserted.



5. After reboot. tap **Install** on the **WPS Pro Updater Screen**.



6. Wait for WPS to launch.



- 7. Finalize the WPS 3 software install.
 - a. Tap the **Home** button.

DSRX1HS	Pending John	Completed Jobs
Printing 696 6x4 (PC)		08.46.31 Job. 427 via POST-w288h432 to RX1HS - POST- w288h432
WPS 2.0 Ver 2.0 20160815 0 9 0 SSID WPS8afe Network (P: 10.116.153.34		DNP Photo Imaging

b. Tap the upper right corner of the screen to go to the **Hidden Menu**.



c. Tap WPS Pro Updater (the console will restrart.)

WPS Pro Updater					
WPS Maintenance		/			
WPS Status					
DNP Launcher					
Settings					
File Manager					
🚊 Linux Deploy					
QuickSupport					
	Ϋ́	¢	\Box	以 》	

8. Tap **DNP WPS Pro Launcher** and then tap **ALWAYS**.



9. If you see this screen, tap **GRANT.** Otherwise, ignore this step.



10. Update Complete. The WPS Pro is now updated to the WPS Pro version 3 software.



Contact Us

Need help? Contact DNP Imagingcomm America Corporation technical support at:

United States Phone: 855-367-7604 Email: dnpsupport@dnp.imgcomm.com Website: www.dnpphoto.com For hours of operation, see our website.